



Mac Install Guide

SOFTWARE VERSION 1.10

December 5, 2017

TABLE OF CONTENTS

Welcome to TGX	1
System Requirements	1
Operating System.....	1
TGX Version Compatibility	2
Receiver Installation Options.....	2
Port configuration	2
Technical Support	2


DOCUMENT REVISION HISTORY

Version	Description of Changes	Author	Date
1.0	Updated formatting	C. Joyner	03/22/2017
1.1	Added version compatibility chart	J. Moder/C. Twine	08/22/2017
1.2	Updated version compatibility chart	J. Moder	12/05/2017

WELCOME TO TGX

TGX installers are available from the Mechdyne “Product Download Center”.
 Contact Mechdyne to receive your login credentials and licenses for the software.

TGX provides separate installers for the Sender and the Receiver. The Sender is the remote workstation whose desktop and applications are shared by TGX to a Receiver. The Receiver is the local computer that displays and interacts with the remote desktop of the Sender via TGX.



SYSTEM REQUIREMENTS

OPERATING SYSTEM

The TGX Mac Receiver supports OS X El Capitan 10.11+.

TGX VERSION COMPATIBILITY

The following matrix depicts the TGX software version compatibility.

TGX Software Version					
	1.6	1.7	1.8	1.9	1.10
1.6	X				
1.7		X	X		
1.8		X	X		
1.9				X	
1.10					X

RECEIVER INSTALLATION OPTIONS

PORT CONFIGURATION

TGX reserves sixteen ports for communication between Sender and Receiver. The default starting port is 40001, however this is configurable. The default port can be modified with the user interface, command line or manually editing the configuration file. All of these methods require elevated permissions. Note, the default port must match between Sender and Receiver.

1. On the TGX Launcher menu bar, select **TGX → Preferences**. Enter the desired port and click **OK**.
2. On the command line, navigate to the bundle and run (as root):
`# TGX.app/Contents/MacOS/tgx_config_helper -p=<port>`
3. Edit `/Library/Application Support/com.mechdyne.TGX/config.ini` (requires elevated privileges), find the `DefaultPort=` line and change the number to the desired port.

TECHNICAL SUPPORT

Mechdyne is available for additional technical support.
Please submit queries through our support portal on the web.

WEB

<http://www.mechdyne.com/software-support.aspx>

EMAIL

software_support@mechdyne.com